

www.opendiscovery.org.uk

Version: 1.0a

Contacts: gareth.price@warwick.ac.uk; a.marsh@warwick.ac.uk

Example 1: Statin + HMG-CoA Reductase

You can follow along with this example by downloading the initial PDB from here. Before starting, watch the video tutorial provided by the authors of AutoDock Vina, here.

Preparing the files

We first need to split the crystal structure of the complex into separate receptor and ligand files. Open up the file 1T02.pdb in your favourite text editor and look at the file. The first section are REMARKS about the structure:

```
HEADER
         OXIDOREDUCTASE
                                               07-APR-04
                                                          1T02
TITLE
         CRYSTAL STRUCTURE OF A STATIN BOUND TO CLASS II HMG-COA
TITLE
        2 REDUCTASE
COMPND MOL_ID: 1;
COMPND 2 MOLECULE: 3-HYDROXY-3-METHYLGLUTARYL-COENZYME A REDUCTASE;
COMPND 3 CHAIN: A, B;
COMPND 4 SYNONYM: HMG-COA REDUCTASE;
COMPND 5 EC: 1.1.1.88;
COMPND 6 ENGINEERED: YES
SOURCE MOL_ID: 1;
SOURCE 2 ORGANISM_SCIENTIFIC: PSEUDOMONAS MEVALONII;
SOURCE 3 ORGANISM_TAXID: 32044;
SOURCE 4 GENE: MVAA;
SOURCE 5 EXPRESSION_SYSTEM: ESCHERICHIA COLI BL21(DE3);
SOURCE 6 EXPRESSION_SYSTEM_TAXID: 469008;
SOURCE 7 EXPRESSION_SYSTEM_STRAIN: BL21(DE3);
SOURCE 8 EXPRESSION_SYSTEM_VECTOR_TYPE: PLASMID;
SOURCE 9 EXPRESSION_SYSTEM_PLASMID: PKK177-3
KEYWDS STATIN, HMG-COA REDUCTASE, COMPLEX, OXIDOREDUCTASE
EXPDTA X-RAY DIFFRACTION
AUTHOR
        L.TABERNERO, V.W.RODWELL, C.STAUFFACHER
REVDAT 2 24-FEB-09 1T02
                           1
                                    VERSN
REVDAT 1 03-AUG-04 1T02
                            0
JRNL
           AUTH L.TABERNERO, V.W.RODWELL, C.V. STAUFFACHER
          TITL CRYSTAL STRUCTURE OF A STATIN BOUND TO A CLASS II
JRNL
JRNL
           TITL 2 HYDROXYMETHYLGLUTARYL-COA REDUCTASE.
JRNL
           REF
                J.BIOL.CHEM.
                                              V. 278 19933 2003
                                ISSN 0021-9258
JRNL
           REFN
           PMID 12621048
JRNL
JRNL
          DOI
                10.1074/JBC.M213006200
REMARK 1
REMARK
        2
REMARK 2 RESOLUTION. 2.60 ANGSTROMS.
```


Delete all the header lines, up to line 765 which is the first atom of the structure.


Copy all lines with ATOM at the start into its own file, named hmg_coa.pdb. Include the TER statement in line 5529. Then, copy the subsequent lines starting with HETATM and LVA in the fourth column into its own file, LVA.pdb:

```
HETATM 5530
             01
                 LVA A 429
                                 86.909 124.095 109.838
                                                          1.00 29.33
                                                                               0
                                                                               0
HETATM 5531
             02
                 LVA A 429
                                 86.507 128.170 108.114
                                                         1.00 20.16
                                                                               0
HETATM 5532
             03
                 LVA A 429
                                 86.864 123.804 107.707
                                                         1.00 27.05
HETATM 5533
             08
                 LVA A 429
                                 84.788 129.227 110.408
                                                         1.00 11.88
                                                                               0
                 LVA A 429
                                 80.841 127.668 105.566
                                                                               0
HETATM 5534
             04
                                                         1.00 36.01
HETATM 5535
             C5
                 LVA A 429
                                 79.054 124.995 108.378
                                                         1.00 19.62
                                                                               C
                                                                               C
HETATM 5536
             C6
                 LVA A 429
                                 78.856 126.160 107.545
                                                          1.00 22.90
HETATM 5537
                                 84.257 128.194 109.522
                 LVA A 429
                                                                               C
             C7
                                                         1.00 17.04
                                                                               C
HETATM 5538
             C8
                 LVA A 429
                                 79.875 124.940 109.429
                                                         1.00 20.40
                                                                               C
HETATM 5539
             C9
                LVA A 429
                                 79.632 127.431 107.958
                                                          1.00 24.43
HETATM 5540
             C10 LVA A 429
                                 86.967 124.566 108.590
                                                         1.00 23.47
                                                                               C
                                                                               C
HETATM 5541
             C11 LVA A 429
                                 80.677 126.143 109.812
                                                         1.00 18.97
                                                                               C
HETATM 5542
             C12 LVA A 429
                                 80.962 127.009 108.579
                                                         1.00 20.64
                                                                               C
                                 85.938 126.854 108.348
HETATM 5543
             C13 LVA A 429
                                                          1.00 18.19
HETATM 5544
             C14 LVA A 429
                                 78.029 126.156 106.515
                                                                               C
                                                         1.00 22.58
HETATM 5545
             C15 LVA A 429
                                 79.964 128.209 106.624
                                                         1.00 29.33
                                                                               c
                                                         1.00 16.97
                                                                               c
HETATM 5546
             C16 LVA A 429
                                 82.827 127.987 109.966
                                                                               C
HETATM 5547
             C17 LVA A 429
                                 85.118 126.936 109.609
                                                         1.00 16.96
             C18 LVA A 429
                                                         1.00 19.74
                                                                               C
HETATM 5548
                                 81.826 128.257 108.857
                                                                               C
             C19 LVA A 429
HETATM 5549
                                 78.612 128.587 106.018
                                                         1.00 28.96
                                                                               C
             C20 LVA A 429
                                 79.918 126.866 110.908
                                                         1.00 18.11
HETATM 5550
HETATM 5551
             C21 LVA A 429
                                 87.077 125.953 108.412
                                                         1.00 19.54
                                                                               C
                                                                               C
HETATM 5552
             C22 LVA A 429
                                 77.823 127.339 105.609
                                                         1.00 27.45
             C23 LVA A 429
                                 78.144 126.939 104.114
                                                                               C
HETATM 5553
                                                         1.00 27.49
                                                                               C
HETATM 5554
             C24 LVA A 429
                                 81.879 128.353 105.045
                                                         1.00 36.32
                                                                               C
HETATM 5555
             C25 LVA A 429
                                 82.754 127.503 104.174
                                                         1.00 33.59
             026 LVA A 429
                                 82.059 129.532 105.295
                                                                               0
HETATM 5556
                                                         1.00 40.47
HETATM 5557
             C27 LVA A 429
                                 82.364 127.528 102.717
                                                          1.00 32.10
                                                                               c
                                                                               C
HETATM 5558
             C28 LVA A 429
                                 82.665 126.087 104.739
                                                         1.00 35.43
            C29 LVA A 429
HETATM 5559
                                 83.114 126.580 101.841
                                                         1.00 28.07
```

Now, put hmg_coa.pdb into a 'receptor' folder and LVA.pdb into a 'pdb' folder. Next, we need to prepare the receptor protein (hmg_coa.pdb).

Open up AutoDockTools, and follow the steps in the image below. Make sure to remember the coordinates and dimensions. Make sure Spacing (Angstrom) is set to 1.000.





Open a new file and enter the box coordinates and dimensions such as:

```
center_x = 83.033
center_y = 125.978
center_z = 106.748

size_x = 16
size_y = 14
size_z = 14
```

Save it as hmg_coa.conf.

You should have a folder that looks like:

Running ODScreen

We can now run the screening. First, let's check that everything is installed properly. In terminal, cd to the Protocol Folder (i.e. the folder with odscreen.py), odparam.py etc.) and run python odcheck.py. Check that there are no failures, and follow the installation guides if there are. You can ignore the warnings. Now, we can run the screening protocol. Navigate to the folder where hmg_coa.conf is located (from before). Now we can run odscreen.py. Make sure you use the correct path to the odscreen.py file.

```
python /protocolfolder/odscreen.py -d . -r hmg_coa -i pdb -c hmg_coa.conf
```

This is the result:

```
# ----- #

# OPEN DISCOVERY #

# Screening Module #

# ------ #

# Version: 1.0 #

# URL: www.opendiscovery.org.uk #

# Contacts: gareth.price@warwick.ac.uk #

# a.marsh@warwick.ac.uk #

# LigDir: /Desktop/example-statin #
```

PDB -> SMILES
Writing smiles/LVA.txt

IMAGES
Writing images/LVA.svg

MOL Writing mol/LVA.mol

MOL2
Writing mol2/LVA.mol2

MINIMISATION
Minimising LVA

PDBQT PREPARATION Writing LVA.pdbqt

SCREENING Processing LVA

EXTRACTING Processing results/LVA/

PDB -> MOL2
Writing results-mol2/LVA.mol2

The resulting files are:

```
combined.mol

    hmg_coa.conf

images

    LVA.svg

mol
 └─ LVA.mol
mol2
 └─ LVA.mol2
od_log.txt
- pdb
 LVA.pdb
pdb-minimised
 pdbqt
 receptor

├── hmg_coa.pdb

 - hmg_coa.pdbqt
results
 ⊢ LVA

── LVA_mode_10.pdb

    LVA_mode_2.pdb
    LVA_mode_3.pdb
    ├─ LVA_mode_4.pdb

── LVA_mode_5.pdb

── LVA_mode_6.pdb

    LVA_mode_7.pdb

── LVA_mode_8.pdb

── LVA_mode_9.pdb

→ hmg_coa.pdb

    ─ log.txt
    out.pdbqt
    complexes
    LVA.pdb
   - summary-sorted.csv
   - summary.csv
   summary.txt
results-mol2
 └─ LVA.mol2
smiles
  LVA.txt
smiles.txt
```

From this point on you can analyse the results. A starting point is to look at the binding energies, sorted and summarised in the summary-sorted.csv file. This should open in any text editor or programs like Excel.